Raspberry PI Camera Motion Tracking and PATT Attestation Setup

1. Setup Raspberry PI

1.1 Plug in the camera module and install the Opency and dependency-lib by below cmd:

```
Raspberry PI install opencv:

sudo pip3 install opencv-contrib-python==3.4.3.18

sudo apt-get install libhdf5-dev

sudo apt-get install libatlas-base-dev

sudo apt-get install libjasper-dev

sudo apt-get install libqt4-test

sudo apt-get install libqtgui4

sudo apt-get update
```

1.2 Copy the **src** folder in raspberry PI. If you want to play the pre-saved video (my_video.h264), set the Test_Mode flag in file **camClient.py** to '**True**':

```
camClient.py - C:\Singtel\Programs\IOT\IOT\RspCamAtt\RspCamAtt\src\camClient.py

File Edit Format Run Options Window Help

import cv2
import udpCom

UDP_PORT = 5005

BUFFER_SZ = udpCom.BUFFER_SZ

TEST_MD = True # Test mode flag
```


1.3 Connect the Raspberry PI to your computer. Run the camera client by cmd:

```
Python3 cameraClient.py

Run the patt checker client by cmd:


Python3 pattClient.py
```

- 2. Run the camera server to connect to the raspberry PI camera.
- 2.1 Open executable\camServer folder and open the config file camServerConfig.txt



Get the raspberry PI's IP address and set the IP address in the config file (replaced the IP in the marked line):

2.2 Save the config file and double click the **camServer.exe** file the camera window will show:



Press "q" button on the keyboard will quit the window.

3. Run the PATT attestation server.

3.1 Open executable\pattServer folder and open the pattServerConfig.txt:

Name	Date modified	Туре	Size
firmwareSample	4/11/2019 3:05 PM	File	12 KB
pattServer.exe	27/3/2020 11:27 AM	Application	4,717 KB
pattServerConfig.txt	27/3/2020 11:42 AM	Text Document	1 KB

Get the raspberry PI's IP address then set the IP address and the firmware name/path you want to check in the config file:

```
pattServerConfig.txt - Notepad

File Edit Format View Help

# PATT server parameters configuration file. fmt: <Tag:val>

# Client IP address. fmt: <IPADDR:(str)***.***.****>
#IPADD:127.0.0.1

IPADD:172.27.143.255

# PATT file split block number.fmt: <BLKNU:(int)**>
BLKNU:4

# Firmware name or path.fmt: <FMPAT:(str)*****>
-MPAT:firmwareSample
```

3.2 double click the **camServer.exe** file the patt check result will show:

```
C:\Singtel\Programs\IOT\IOT\RspCamAtt\RspCamAtt\executable\pattServer\pattSe

Local_PATT: 3D7A2E00008383017101046F6F3E720800007A506400007
0104075A646120657769

CameraPATT: 3D7A2E00008383017101046F6F3E720800007A506400007
0104075A646120657769

Patt check result: verifierChechsum == camreaCheckSum

The camera firmware attestation successful

Finished
```